Document to Knowledge™
A CANON COMPANY

IRISPowerscan - EMS

Manual Activation of License

Revision History

Date	Description	Author
20180223	V0.1 – Creation	TW
20180307	V0.2 – Feedback implementation	TW
20190827	V1.0 – Updates for IPS11	TFR

I.R.I.S. SA/NV
Rue du Bosquet 10
B-1348 Louvain-la-Neuve

P: +32 (0) 10 45 13 64
F: +32 (0) 10 45 34 43

www.irisdatacapture.com

IRIS
Document to Knowledge™
A CANON COMPANY

Table of Contents

1. Introduction 3
2. Target Audience 3
3. How to manually activate IRISPowerscan with an EID 4
3.1 Step 1: Login 4
3.2 Step 2: User Registration 4
3.3 Step 3: Manual Activation 5
4. Legal Notice 8
4.1 Copyright 8

I.R.I.S. SA/NV
Rue du Bosquet 10
B-1348 Louvain-la-Neuve

P: +32 (0) 10 45 13 64
F: +32 (0) 10 45 34 43

www.irisdatacapture.com

Document to Knowledge™
A CANON COMPANY

1. Introduction

To be able to **activate your License number manually at anytime,** you need to access an online tool called **Sentinel EMS**.

In this tool, your Activation (or License) code is called an **Entitlement ID (EID).**

This online activation tool is only for activating IRISPowerscan, it cannot be used for revocation.

2. Target Audience

This documentation is intended for Consultants in IRIS products who install and manage IRIS products at a client or customers who install IRISPowerscan themselves.

Canon
CANON GROUP


3. How to manually activate IRISPowerscan with an EID

3.1 Step 1: Login


1) Go online to

   https://irissa.prod.sentinelcloud.com/ems/customerLogin.html

2) In the **Customer Login window**, select **EID** in the drop-down list.



3) Paste your **EID** in the Entitlement ID text box
4) Click **Login**




3.2 Step 2: User Registration

1) **Register** now or later (see **Register later** on the upper right corner)


   If you are an IRIS or Canon employee doing the manual activation, register with the customer information.

Registering is required to ease the access to **Technical Support**.




3.3 Step 3: Manual Activation


1) In the Associated Product and Features details, the corresponding product is selected. click **Activate**.




2) In **IRISPowerscan**, find the **Computer ID** by going to **Info\Features\Activate\Manual Activation**




3) In **EMS**, copy and paste this **Computer ID** with the first star * in the **Client 1 info** text box. Enter 1 as Quantity as shown. Leave all the other text boxes or check boxes empty as shown.



4) Click **Activate**



5) In **IRISPowerscan,** Copy and Paste the **License String** (from *D or *I up to the end) in the **License code** box and click **Activate**



4. Legal Notice

4.1 *Copyright*

© 2019 I.R.I.S. SA. All Rights Reserved

I.R.I.S. SA/NV
Rue du Bosquet 10
B-1348 Louvain-la-Neuve

P: +32 (0) 10 45 13 64
F: +49 (0) 10 45 34 43

www.irisdatacapture.com